CMUSIC production

CMP Small Saw

Small Saw

User`s manual

All Right Reserved © CMusic Production 2017

CMUSIC production

CMP Small Saw

Thank you for downloading our **Small Saw** Instrument!
Typically used by artists in folk and rural country genres, it's unique and distinctive sound is created using a violin bow. We decided to make this rare musical tool and see what will come of it. Enjoy!

Saw performed by: Igor Talashov
Recording: Eugene Drayer
Editing: Vladimir Kuznetsov
Programming, Design & Script: Vladimir Kuznetsov
© 2017 Cmusic Production, LLC / All Rights Reserved,
Cmusic Production®

Watermark Protected.

Features

- Legato, Portamento and Glissando Velocity Control
- Gliss-Up articulation
- Saw FX
- 257 MB on disc, 487 samples, 44.1 KHz / 24-bit

Requipements

- Native Instruments **full retail Kontakt 5.0** or high
- Windows 7 or 8, Intel Core Duo or AMD Athlon 64 X2, 4 GB
- Mac OS X 10.6, Intel Core 2 Duo, 4 GB
- 5 GB free disk space

All Right Reserved © CMusic Production 2017

CMUSIC production

CMP Small Saw

Installation Notes

1. Please go to the download links you received after purchase and download all of the files.

2. Make sure you put all downloaded files into a single folder.

3. Unpack the downloaded file "**CMP_Small_Saw.rar**" to any folder. Place .nki file next to the Samples folder.

To extract your files we recommend using Winrar for PC users, or UnrarX or Rar-Expander for the Mac.

4. You need to have the full retail version of Kontakt 5.0 or later to use this library. **The free Kontakt Player does NOT support this library.**

5. Open the Kontakt 5 browser (look on the left-hand side of the Kontakt user interface) and click the "Files" tab. Find the library folder, which you extracted earlier, and double-click on the **Small Saw.nki** file which should be in that folder. You can use the Quick-Build Database option to allow Kontakt to find and store the location for faster browsing and loading.

You cannot use the "Libraries" tab to "Add Library" for this product. That feature is only available for encoded & locked "Powered-By-Kontakt" libraries.

Watch a video to learn how to add to **Kontakt Quick-Load** menu: https://www.youtube.com/watch?v=4USeGpi9EnM.

All Right Reserved © CMusic Production 2017

LEGATO

If you use the **X-Fade** method:

Default:
Glissando (Vel 0 – 20),
Portamento (Vel 21 – 50),
Legato (Vel 51 – 127)

Change Value between Glissando, Portamento and Legato



If you use the **Velocity** method:
Default: play Legato
Use **E2** (Vel 0 – 63) to play Portamento.
Use **E2** (Vel 64 – 127) to play Glissando.

Gliss-Up
Use **D2** (Vel 0 – 63) keyswitch to play **Gliss-Up**.

Saw-FX
Use **D2** (Vel 64 – 127) keyswitch to play **Saw FX**.

All Right Reserved © CMusic Production 2017

Convolution Reverb

Turn on Convolution Reverb, and adjust the balance between the DRY and WET signals as desired.

All Right Reserved © CMusic Production 2017